



## Pages-windows installation



1. Select the Control Panel under the Main grouping icon .



2. Select Printers




3. Select install an a box will pop up requesting where the install disk is located. Enter the location of the installation files.

Example 1. A:\

The installation files are located on a floppy disk in drive A:

Example 2. C:\pages-win


The installation files are located on the hard drive C: in the directory pages-win.




4. A list of printer will be displayed. Using the mouse select a printer and then select "OK". The selected print driver will be installed.



5. Continue steps 3 and 4 until all the listed printers are installed. When finished all the installed printer will appear in the printers window.



6. Select one of the newly install printers and select "Connect...". From the Connect window select "Network".




7. This will open a window titled “Connect a printer”. Select “New LPR Printer” under the “Session” menu.

The screenshot shows a window titled "Connect a printer" with a menu bar containing "Session", "Resources", "Settings", and "Help". Below the menu bar, there are two dropdown menus: "Local name:" with "LPT1:" selected and a downward arrow, and "Printer type:" with "NFS Printer" selected and a downward arrow. Below these is a text field labeled "Printer or print command". Underneath is a section titled "Previous connections" with an empty list box. Below that is a section titled "Current connections" with an empty list box. At the bottom, there are five buttons: "Connect", "Disconnect", "Other NOS", "Help", and "Done".


8. Fill in the requested information as shown below. Select an unused port on your computer. When all the information is entered select “OK”.

The screenshot shows a window titled "Configure LPR Printer". It contains several input fields and buttons. The "Print Session:" field is set to "Pages-Windows". The "Hostname:" field is set to "pages-server". The "Printer name:" field is set to "pages-adobe". The "Port:" field is set to "LPT3:" with a downward arrow. There is a checkbox labeled "Make permanent" which is checked. On the right side, there are four buttons: "OK", "Cancel", "Advanced >>", and "Help".


9. The new LPR printer is added to the list of Previous connection in the “Connect a printer” window. Select the new connection and then select “Connect” at the bottom of the window. If the connection was successful the printer will be listed under Current connections and “Connection succeeded” will be displayed at the bottom of the window.



10. Under the “Settings” menu select “User Information...”. Enter your Z# where the Name is requested. You do not need to fill out a password just press “OK”. Exit the “connect a Printer window.



11. Now the port we selected, LPT3 shows that it is connected to “\\pages-server\pages-adobe”. Select LPT3 and press the “OK” button. You have now connected the first pages printer to LPT3.



12. For each of the pages printers.  
Select the printer then select “Connect”  
Select the LPT3 port then select “OK”

13. As shown below all the pages printer appear as installed printers. Each one is connected to the printer port being used for PAGES network printers.

